



Viz Licensing Administrator Guide

Version 3.1



Copyright ©2024 Vizrt. All rights reserved.

No part of this software, documentation or publication may be reproduced, transcribed, stored in a retrieval system, translated into any language, computer language, or transmitted in any form or by any means, electronically, mechanically, magnetically, optically, chemically, photocopied, manually, or otherwise, without prior written permission from Vizrt.

Vizrt specifically retains title to all Vizrt software. This software is supplied under a license agreement and may only be installed, used or copied in accordance to that agreement.

Disclaimer

Vizrt provides this publication “as is” without warranty of any kind, either expressed or implied. This publication may contain technical inaccuracies or typographical errors. While every precaution has been taken in the preparation of this document to ensure that it contains accurate and up-to-date information, the publisher and author assume no responsibility for errors or omissions. Nor is any liability assumed for damages resulting from the use of the information contained in this document. Vizrt’s policy is one of continual development, so the content of this document is periodically subject to be modified without notice. These changes will be incorporated in new editions of the publication. Vizrt may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time.

Vizrt may have patents or pending patent applications covering subject matters in this document. The furnishing of this document does not give you any license to these patents.

Antivirus

Vizrt does not recommend or test antivirus systems in combination with Vizrt products, as the use of such systems can potentially lead to performance losses. The decision for the use of antivirus software and thus the risk of impairments of the system is solely at the customer's own risk.

There are general best-practice solutions, these include setting the antivirus software to not scan the systems during operating hours and that the Vizrt components, as well as drives on which clips and data are stored, are excluded from their scans (as previously stated, these measures cannot be guaranteed).

Technical Support

For technical support and the latest news of upgrades, documentation, and related products, visit the Vizrt web site at www.vizrt.com.

Created on

2024/07/23

Contents

| | | |
|----------|---|-----------|
| 1 | Introduction..... | 5 |
| 1.1 | Improvements and Bug Fixes | 5 |
| 2 | License Options | 6 |
| 2.1 | Supported Setups | 6 |
| 2.2 | Hardware Dongle | 6 |
| 2.3 | Software Container | 6 |
| 3 | System Requirements | 8 |
| 3.1 | CodeMeter Runtime | 8 |
| 3.2 | Supported Products | 8 |
| 3.3 | Supported Browsers for the License Portal | 9 |
| 4 | Vizrt License Portal | 10 |
| 4.1 | Vizrt License Portal Landing Page..... | 11 |
| 4.1.1 | License Portal | 11 |
| 4.1.2 | Logging into the License Portal | 11 |
| 4.1.3 | Auto Update | 12 |
| 4.1.4 | Troubleshooting | 14 |
| 4.2 | Licenses..... | 15 |
| 4.3 | Containers | 17 |
| 4.4 | Free Licenses | 18 |
| 4.5 | Online License Activation | 19 |
| 4.5.1 | Activating a License using Online Activation | 19 |
| 4.6 | Offline License Activation..... | 22 |
| 4.6.1 | Activating a License using Offline Activation | 22 |
| 4.7 | Admin..... | 30 |
| 4.7.1 | Information..... | 30 |
| 4.7.2 | Licenses..... | 31 |
| 4.7.3 | Tickets..... | 32 |
| 4.7.4 | Users | 33 |
| 4.7.5 | Customers | 34 |
| 4.8 | Customers | 35 |
| 4.9 | Account | 36 |
| 4.10 | Re-Hosting..... | 38 |
| 5 | CodeMeter WebAdmin | 42 |

| | | |
|----------|--|-----------|
| 5.1 | Configuration | 44 |
| 5.1.1 | Basic Configuration..... | 44 |
| 5.1.2 | Server | 47 |
| 5.1.3 | Advanced..... | 49 |
| 5.2 | Container..... | 52 |
| 5.3 | Dashboard | 54 |
| 5.4 | Diagnosis | 55 |
| 5.4.1 | CmDust Log Export..... | 56 |
| 5.5 | License Monitor | 57 |
| 5.5.1 | All Licenses..... | 57 |
| 5.5.2 | Sessions | 58 |
| 6 | Troubleshooting | 60 |
| 6.1 | License Activation Issues | 60 |
| 6.2 | Refreshing Licenses Page | 60 |
| 6.3 | Changing WIBU CodeMeter Runtime | 60 |
| 7 | FAQ | 62 |
| 7.1 | Can Licenses be Updated during Operation? | 62 |
| 7.2 | Local License on Virtual & Cloud Environments | 62 |
| 7.3 | How to Handle a Corrupted WIBU Software Container? | 62 |
| 7.4 | Upgrading Sentinel Licenses to WIBU Licenses..... | 62 |
| 7.4.1 | Upgrade Process Steps:..... | 63 |

1 Introduction

Vizrt is releasing an update to the License Portal that enables customers to manage licenses, using [WIBU Systems](#). This documentation guides you through the different options and processes.

1.1 Improvements And Bug Fixes

Kindly check the [Vizrt Licensing Release Notes](#) for the latest changes.

This software protection program is implemented in Vizrt software as part of major new releases. Prior versions covered by software protection can continue to run on the node-locked licensing.

2 License Options

- [Supported Setups](#)
- [Hardware Dongle](#)
- [Software Container](#)

2.1 Supported Setups

| Client Type | Hardware Dongle | Software Container | License Server |
|-----------------------------|-----------------|--------------------|----------------|
| On-Premise | | | |
| Physical local machines | ✓ | ✓ | ✓ |
| Virtualized local machines | ✓ | ✓ | ✓ |
| Physical license servers | ✓ | ✓ | |
| Virtualized license servers | ✓ | ✓ | |
| Cloud | | | |
| Client machines | | ✓ | ✓ |
| License servers | | ✓ | |

2.2 Hardware Dongle

These are recommended for on-premise license servers, as they can be attached to a backup server without further restrictions.

License Dongles can also be used on local machines.

2.3 Software Container

For dongle-less workflows, a Software Container is recommended, usable for License Servers and local usage.

For virtualized environments and cloud environments, a dedicated Software Container called Smartbind_Loose is required. This container type can be added to individual users as a permission, which allows the user to create this container type and activate licenses on it.

 **Quick Troubleshooting**

Info: Software container protection is performed on the hardware elements on validation. If the hardware is changed, the WIBU container validation may fail, making licenses unavailable.

3 System Requirements

The WIBU V3 license items provide a faster license activation and allows Vizrt software products to allocate the licenses faster. In addition, the features were reduced to reduce complexity.

These are the supported products and browsers.

3.1 CodeMeter Runtime

Running Vizrt Software requires WIBU CodeMeter Runtime 7.51 or later.

3.2 Supported Products

| Vizrt Product | First Version Supporting WIBU V2 | First Version Supporting WIBU V3 |
|----------------------|----------------------------------|----------------------------------|
| Viz Engine | 3.10.0 | 5.x |
| Graphic Hub | 3.1.0 | 3.8.0 |
| Viz Virtual Studio | 1.1.1 | 1.6.1 |
| Media Sequencer | 5.4.0 | TBA |
| Viz Trio | 4.0.0 | 4.2.0 |
| Viz Multiplay | See MSE | 3.1. |
| Viz Pilot Edge | See MSE | TBA |
| Viz Libero | 6.11.2 | TBA |
| Viz Arena | 5.0.0 | TBA |
| Viz Arc | 1.0.0 | TBA |
| Viz Vectar | 1.0.0 | TBA |
| Viz Datacenter | 1.0.0 | 2.0.0 |
| Viz Channel Branding | | 5.0 |

| Vizrt Product | First Version Supporting WIBU V2 | First Version Supporting WIBU V3 |
|---------------|----------------------------------|----------------------------------|
| Viz Story | | 3.1 |

3.3 Supported Browsers For The License Portal

- Google Chrome
- Firefox
- Microsoft Edge

4 Vizrt License Portal

This section contains information on the following topics:

- [Vizrt License Portal Landing Page](#)
- [Licenses](#)
- [Containers](#)
- [Free Licenses](#)
- [Online License Activation](#)
- [Offline License Activation](#)
- [Admin](#)
- [Customers](#)
- [Account](#)
- [Re-Hosting](#)

4.1 Vizrt License Portal Landing Page

This page contains the following information:

- [License Portal](#)
- [Logging into the License Portal](#)
 - [Artist Free Login](#)
 - [Vizrt Community Login](#)
- [Auto Update](#)
- [Troubleshooting](#)

4.1.1 License Portal

The License Portal can be reached at <https://license.vizrt.com>.

Home Auto Update

Welcome to License Portal

If you are an Artist Free user please enter your username and password here. This will give you access to Artist Free licenses only.

Email Address Password Login

If you are a commercial Vizrt Customer with Community access, please click the Community Login button below.

Community Login

4.1.2 Logging into the License Portal

Artist Free Login

Users of Artist Free can log in using the marked login with the credentials used to sign up for Artist Free:

Home Auto Update

Welcome to License Portal

If you are an Artist Free user please enter your username and password here. This will give you access to Artist Free licenses only.

Email Address Password Login

If you are a commercial Vizrt Customer with Community access, please click the Community Login button below.

Community Login

Vizrt Community Login

For Vizrt customers with access to other Vizrt Community Services, the Community Login page should be used.

Home Auto Update

Welcome to License Portal

If you are an Artist Free user please enter your username and password here. This will give you access to Artist Free licenses only.

Email Address Password Login

If you are a commercial Vizrt Customer with Community access, please click the Community Login button below.

Community Login

✔ **Tip:** If you already have an account for <https://community.vizrt.com>, you can use the same credentials.

Once in the license portal, you can use the **Community Login** button and the SSO of Vizrt to log into the portal.

vizrt

User name

password


Register

save data


[Did you forget your password?](#)

4.1.3 Auto Update

Vizrt Licensing Portal offers the functionality to update licenses without logging into the portal.




The Auto Update checks the locally installed CodeMeter Runtime for connected Software Containers and WIBU Dongles. Detected Containers and Dongles are displayed below the information text. If multiple are detected, the drop-down menu can be used to select the Container or Dongle that needs to be updated. Pressing **Check License Update** searches for available updates for the Container or Dongle selected.



Info: The Auto Update function checks if there were any changes to the expiration date or the quantity since the last license update. In addition, features that were removed are also detected and removed from the container or dongle.


When an Auto Update is detected a short summary is displayed. This summary shows the licenses that are going to be added, changed and removed.




Info: In the screenshot above, the Quantity of the Graphic Hub License is going to be 5 after the Auto Update is completed, and the expiration date is set to April 30th 2024.

Clicking **Activate Selected Licenses Now** starts the Auto Update process on the Container or Dongle.

After a short time, the auto update is complete. Depending on the amount of changes, the process can take longer.



If a Container or Dongle is not located in the machine the Auto Update is executed, the Offline Activation can be used. To select the Offline Activation for Auto Update click on **File-based license transfer**.



After that, the Offline Activation can be executed as documented in the [Offline Activation](#) section.

4.1.4 Troubleshooting

If you encounter any issues in the license portal, please use the Vizrt Community Portal (<https://community.vizrt.com>) and open a support case stating the issue.

4.2 Licenses

The licenses page provides an overview of licenses of the account the user is assigned to. The licenses are sorted by ticket ID showing all features each ticket has assigned.

The screenshot shows the 'Licenses' page in the Vizrt interface. It features a table with the following columns: Ticket, Name, Order ID, QTY, End Date, Activated On, Container, and Status. The table is grouped by ticket ID, with expandable sections for each ticket. The first group, under ticket ID 4V63S-2M97P-8BAS2-U373C-LGQ6C (5), lists features like 'V3 TriCaster Now - TriCaster Now Bridge - (Network)', 'V3 Viz Arena - Developer Features - (Network)', 'V3 Viz Engine - Artist Preview - (Network)', and 'V3 Viz Arena - Developer Features - (Network)'. The second group, under ticket ID B4EW6-KH694-N279S-7RY33-U226H (5), lists features like 'Viz Engine lmi1 - 4K Video Enablement - (Network)', 'Viz Engine lmi1 - Artist - (Network)', 'Viz Engine lmi1 - Artist Preview - (Network)', 'Viz Engine lmi1 - Bone&Skin Live Motion Capture - (Network)', and 'Viz Engine lmi1 - Chroma FX - (Network)'. The interface includes a search bar, a 'Show 10 entries' dropdown, and pagination controls at the bottom.


| Column Name | Description |
|---------------------|---|
| Ticket | This column displays the license Ticket ID. One Ticket can hold multiple license features. |
| Name | This column describes the name of different license features. The license features enable different features of Vizrt products. License features have two attributes: Expiration Date and Quantity. |
| Order ID | This column shows the Order ID the license belongs to. |
| QTY | The Quantity column displays how often a license feature is licensed on the ticket. |
| End Date | This column displays the expiration date of the license features. |
| Activated On | This column displays the activation date of a license feature. |

| Column Name | Description |
|-------------|--|
| Container | This column displays the Software Container or Dongle the license feature is applied on. |
| Status | This column displays the current state of a license feature. |

The columns can be filtered alphabetically using the arrow buttons on the column title. Columns can be hidden by clicking the **Column visibility** button on the top left.


It is possible to select how many **entries per page** should be displayed. You can use the **search bar** to search the individual columns.

With the option field on the top right, you can filter license features according to date or specify certain states of licenses.



4.3 Containers

The containers page shows the currently used license containers. This means that all license dongles that hold a license ticket of the account the user is assigned to, are displayed.




| Column | Description |
|-----------|--|
| Type | This column displays the type of container that the license ticket is applied on. There are currently 3 types of Containers: Local Software Container, USB Dongle, Smartbind_Loose Container (used for VMs and Cloud instances). |
| Serial | This column displays the serial number of the Container or Dongle. |
| Host Name | This column displays the Host Name of the computer the Software Container is located. This does not work for USB dongles. |
| Licenses | This column displays the License features and the tickets they originate from. |

The columns can be filtered alphabetically using the arrow buttons on the column title. Columns can be hidden by clicking the **Column visibility** button on the top left.


It is possible to display more than ten entries per page. You can use the search bar to search the individual columns.

4.4 Free Licenses


Here you are able to create Free Licenses for private or educational use. Currently this option is available for Free Viz Artist.



To create your own free license, click on **Create License**.



After a few seconds the license ticket is shown.




After creating a license, they are visible on the [Licenses](#) and can be activated.

4.5 Online License Activation


4.5.1 Activating a License using Online Activation

You can activate a new license ticket on a Dongle, Software Container or a Smartbind_Loose Container.

On the [licenses page](#), below the license information, there are the **Activate Licenses** and **Auto Update** buttons.



1. To start the license activation click the **Activate Licenses** button.
2. Next, you can select the destination of the license. These are the options available:



| Container Type | Description |
|------------------------------|---|
| CmDongle | Activates the license on a USB Dongle. |
| CmActLicense local | Activates the license on a local Software Container. |
| CmActLicense Smartbind Loose | Activates the license on a Software Container in a Cloud or VM environment. |

Info: The Smartbind Loose Container type is bound to a specific permission which needs to be enabled per user and is not enabled by default. This Container type is used to create a Software Container in a Cloud or VM Environment.

- After selecting a container, the next page displays all licenses currently available for activation. The table displays all licenses available for activation, including expiration date and quantity.


The screenshot shows the 'Available Licenses' page in the Vizrt interface. At the top, there are navigation tabs for 'Licenses', 'Containers', and 'Free Licenses'. Below the header, there's a search bar and a 'Column visibility' dropdown set to 'Show 10 entries'. The main part of the page is a table with the following columns: Ticket, Name, Order ID, QTY, End Date, Activated On, Container, and Status. The table contains 10 rows of license information, each with a checkbox in the 'Ticket' column. Below the table, there's a pagination control showing 'Showing 1 to 10 of 8,825 entries' and a 'Next' button. At the bottom, there's a 'Select CmContainer' dropdown and a 'Get CmContainer automatically' button. A 'Next' button is also present at the bottom left.

The **Column visibility** allows you to select or deselect the columns in the table. This can be used for better visibility. With the **Search** field you can search for ticket IDs or License features.

Tip: It is recommended to always use the search field, for the ticket ID to not mistakenly activate unwanted license features.

- Using the check-box in the first column, select the features to activate.
- Once the features are selected, you can activate them on a new container (created automatically in the next step), or select an existing container to add the licenses to.


6. Click **Next** to continue to the activation Summary page.



The summary page shows the licenses that are going to be added, changed or removed. For the activation process, licenses are added.

7. Click **Activate Selected Licenses Now** to activate the licenses.

8. Once the activation steps are complete, a short message is displayed.



9. Pressing **OK** returns the portal to the [Licenses](#).

4.6 Offline License Activation

4.6.1 Activating a License using Offline Activation

With the offline license activation, you can activate a license in an environment that does not have internet access. However, it is required to use one computer with internet access in parallel to allow a file transfer between the Vizrt License Portal and the offline environment.

On the [licenses page](#), below the license information, there are the **Activate Licenses** and **Auto Update** buttons.

The screenshot shows the 'Licenses' section of the Vizrt interface. At the top, there are navigation tabs for 'Licenses', 'Containers', and 'Free Licenses'. Below the navigation, there is a search bar and a 'Column visibility' dropdown set to 'Show 10 entries'. The main content is a table with columns: Ticket, Name, Order ID, QTY, End Date, Activated On, Container, and Status. The table lists several licenses for 'Viz Arena lmi1', including '4K Resolution (Add-on)', 'Arena Core', 'Developer Features', 'Multiple Outputs (Option)', and various sports add-ons like 'Sport Australian Football', 'Sport Badminton', 'Sport Beach Volleyball', 'Sport Candian Football', 'Sport Cricket', and 'Sport Custom'. All licenses are listed with a quantity of 1 and a status of 'Activated'. At the bottom of the table, there are two buttons: 'Activate Licenses' and 'Auto Update'.

1. To start the license activation click the **Activate Licenses** button.
2. Next, you can select the destination of the license. These are the available options:

The image shows three options for license activation, each with an icon and a description:

- CmDongle**: I want my licenses in a dongle to be able to use them offline on different computers. (Icon: USB dongle)
- CmActLicense**: I want my licenses offline on one computer. (Icon: Document with gear)
- CmActLicense**: I want my licenses offline on one computer. (Icon: Document with cloud)

- In this view, instead of selecting and activating the available licenses directly, click **File-based license transfer**.

The screenshot shows the 'Available Licenses' section of the Viz Licensing Administrator. At the top, there are navigation tabs for 'Licenses', 'Containers', and 'Free Licenses'. Below the tabs, there's a search bar and a 'Column visibility' button. A table displays a list of licenses with the following columns: Ticket, Name, Order ID, QTY, End Date, Activated On, Container, and Status. The table contains 10 rows of licenses, all with a quantity of 1 and an end date of 2024-04-24. Below the table, there's a 'Showing 1 to 10 of 8,824 entries' indicator and a pagination control. At the bottom, there's a 'Select CmContainer' dropdown menu and a 'Next' button. A red box highlights the 'File-based license transfer' button in the bottom right corner.


| Ticket | Name | Order ID | QTY | End Date | Activated On | Container | Status |
|-------------------------------|--|----------|-----|------------|--------------|-----------|-----------|
| 22N82-YLFMG-KGD8C-W9LLQ-8HNMG | Viz Arena Im1 - Sport Australian Football (Add-on) - (Network) | | 1 | 2024-04-24 | - | | Available |
| 22N82-YLFMG-KGD8C-W9LLQ-8HNMG | Viz Arena Im1 - Sport Badminton (Add-on) - (Network) | | 1 | 2024-04-24 | - | | Available |
| 22N82-YLFMG-KGD8C-W9LLQ-8HNMG | Viz Arena Im1 - Sport Beach Volleyball (Add-on) - (Network) | | 1 | 2024-04-24 | - | | Available |
| 22N82-YLFMG-KGD8C-W9LLQ-8HNMG | Viz Arena Im1 - Sport Candian Football (Add-on) - (Network) | | 1 | 2024-04-24 | - | | Available |
| 22N82-YLFMG-KGD8C-W9LLQ-8HNMG | Viz Arena Im1 - Sport Cricket (Add-on) - (Network) | | 1 | 2024-04-24 | - | | Available |
| 22N82-YLFMG-KGD8C-W9LLQ-8HNMG | Viz Arena Im1 - Sport Custom (Add-on) - (Network) | | 1 | 2024-04-24 | - | | Available |
| 22N82-YLFMG-KGD8C-W9LLQ-8HNMG | Viz Arena Im1 - Sport FIBA Basketball (Add-on) - (Network) | | 1 | 2024-04-24 | - | | Available |
| 22N82-YLFMG-KGD8C-W9LLQ-8HNMG | Viz Arena Im1 - Sport Fieldhockey (Add-on) - (Network) | | 1 | 2024-04-24 | - | | Available |
| 22N82-YLFMG-KGD8C-W9LLQ-8HNMG | Viz Arena Im1 - Sport Horseracing (Add-on) - (Network) | | 1 | 2024-04-24 | - | | Available |
| 22N82-YLFMG-KGD8C-W9LLQ-8HNMG | Viz Arena Im1 - Sport IHF Handball (Add-on) - (Network) | | 1 | 2024-04-24 | - | | Available |

- The offline activation follows the same steps as the online activation process, but requires to manually transfer the files between the license portal and the remote computer with the license container. As a first step, it is required to select the features that should be activated.


You can filter the data columns using the **Column Visibility** button and search for tickets or features using the **Search** field.

Below the data table it is possible to either, select a Container that is already known to the organization (which means there is already another license of this account applied), or start

the activation from a file from the local CodeMeter Control Center of the remote computer.




- In the remote computer open the CodeMeter Control Center. This can be done by opening the Windows Search and searching for **CodeMeter Control Center**. Select the Dongle or Software Container the license should be activated on and click **License**

Update.


Info: To generate a Software Container on a local machine, use the Offline Licensing Helper Tool that can be downloaded from the [Accounts](#) page of the license portal.

Warning: It is not possible to use the Offline Licensing Helper to create a Software container on a VM or Cloud environment. For that, please use the [Online activation](#) in any case.

- After the welcome message, select **Create license request** and click next.




- Select the path where the Request file should be stored and click **Commit** to generate the file.




- Copy the created file to the computer with the license portal open, and upload it using **Select File**. Click **Start Activation Now**.

If the container is already known to the system, it can be selected above the **Select File** field.




- Once the file is successfully uploaded, the portal continues to the next interface. Click **Download License Update File Now** to download the License Update file. Once the file is downloaded click **Next**.




- Copy the downloaded License Update file to the remote computer and open CodeMeter Control Center. Click **License Update** again and then select **Import license update**.

Select the file that has just been downloaded from the license portal and press **Commit**.




11. After successfully importing the update file, click **License Update** again and select **Create receipt**. Choose the path where the receipt file should be saved and press **Commit**.


The receipt file is required to confirm if the license activation was successful.



- Copy the receipt file from the remote computer to the one with the license portal still open, and upload the receipt file by using **Pick license receipt file**.




- Once uploaded, click **Upload Receipt Now**. This finishes the activation of the license. Clicking **OK** redirects the portal to the licenses page.



4.7 Admin

The Admin Page allows administrator users of the license portal to manage licenses and tickets of their account and all of its child accounts. The administrator access is tied to a permission which can be granted to individual users upon request.

The Account name is displayed, and the information is separated in five different sections.



| Section | Description |
|---------------------------|---|
| Information | Provides information about the account the logged in user is assigned to. |
| Licenses | Displays all licenses of the account. |
| Tickets | Displays all tickets of the accounts. |
| Users | Displays the users of the account. |
| Customers / Organizations | Displays the Child Accounts. |

4.7.1 Information

The Information tab displays the name, description, the date it was created and the maintenance period of the account. The name is the account number used by the system, while the description displays the account name.

Reseller - Vizrt Company (ISV)

| Information | |
|--------------------------|---------------------|
| Name | 1 |
| Description | Vizrt Company (ISV) |
| Created | 2022-09-02 |
| Maintenance Period (End) | 2025-04-01 |

Licenses

Tickets

Users

Customers

i Info: The Maintenance Period is written on each license ticket and allows customers to use Vizrt Software Products that were released before that date. The Maintenance Period within the portal is updated according to the Support Contract of an account, this is not directly reflected on licenses that have already been applied. To use the latest Vizrt Software Products, the applied licenses need to be update with the latest maintenance period.

4.7.2 Licenses

The licenses section provides the same information as the [Licenses](#) tab but for Administrator users.

The screenshot shows the 'Admin' tab in the Vizrt interface. Under the 'Licenses' section, there is a table with the following columns: Name, Ticket, Creator, Order ID, Creation Date, Units, Usage (days), End Date, QTY, Cancellation Until, Activation Date, CmContainer, and Status. The table lists several licenses, including 'Data Center - Data Center Core - (Network)', 'PMO - phantasy item - (Network)', and 'V3 3Play by Viz Now - 3Play by Viz Now - (Network)'. At the bottom of the table, there is a 'Manage all Licenses' button.

| Name | Ticket | Creator | Order ID | Creation Date | Units | Usage (days) | End Date | QTY | Cancellation Until | Activation Date | CmContainer | Status |
|--|-------------------------------|-------------------|--------------|---------------|-------|--------------|------------|-----|--------------------|-----------------|----------------|--------|
| Data Center - Data Center Core - (Network) | 5AFE4-2ZDA7-A4FG9-N5A39-6LRMZ | vizrtAdmin@lp.com | | 2023-09-20 | - | - | 2024-09-21 | 3 | 2024-09-21 | - | | active |
| Data Center - Data Center Core - (Network) | LYXPL-HD3B5-QMYUB-2SCUH-2UUWV | vizrtAdmin@lp.com | | 2023-04-17 | - | - | 2024-11-10 | 1 | 2024-11-10 | - | | active |
| Data Center - Data Center Core - (Network) | 22V4H-9F88G-F5RCW-TBYAM-ZF7BM | pmo@vizrt.com | | 2024-03-11 | - | - | 2024-03-18 | 1 | 2024-03-18 | - | | active |
| Data Center - Data Center Core - (Network) | BZGM6-4FJZS-8DHVZ-HYG5P-G2NZU | pmo@vizrt.com | | 2024-03-11 | - | - | 2024-03-18 | 1 | 2024-03-18 | - | | active |
| PMO - phantasy item - (Network) | 2SQY7-WSUKE-3GFTT-CFF7B-HQ9FC | pmo@vizrt.com | | 2024-02-20 | - | - | 2025-02-21 | 1 | 2025-02-21 | - | | active |
| PMO - phantasy item - (Network) | RRBVC-HR3V3-7EG82-6YW2K-L3JDN | vizrtAdmin@lp.com | | 2023-09-25 | - | - | 2024-09-26 | 1 | 2024-09-26 | 2023-10-02 | 130-3819564413 | active |
| V3 3Play by Viz Now - 3Play by Viz Now - (Network) | EKAH9-89DAR-D7KK8-WF2QA-SZ239 | vizrtAdmin@lp.com | CMLC-2023041 | 2023-04-12 | - | - | 2024-04-19 | 1 | 2024-04-19 | - | | active |
| V3 3Play by Viz Now - 3Play by Viz Now - (Network) | RHFZA-S764C-M6ZBL-NYS73-4QBS9 | vizrtAdmin@lp.com | | 2023-03-02 | - | - | 2099-12-31 | 1 | 2099-12-31 | - | | active |
| V3 3Play by Viz Now - 3Play by Viz Now - (Network) | XTGRR-H37LF-3F88W-XT3YE-7RM7D | pmo@vizrt.com | | 2023-03-16 | - | - | 2024-03-31 | 1 | 2024-03-31 | - | | active |
| V3 Data Center - Data Centre Core - (Network) | 5AFE4-2ZDA7-A4FG9-N5A39-6LRMZ | vizrtAdmin@lp.com | | 2023-09-20 | - | - | 2024-09-28 | 5 | 2024-09-28 | - | | active |

With the **Manage all Licenses** button, Administrators can activate the licenses from the Admin tab. This button takes you to the Activation Page for [Online License Activation](#) and [Offline License Activation](#).

For accounts that also have an account hierarchy, all available tickets from the Parent Account and Child Accounts are available for activation.

4.7.3 Tickets

The Ticket section allows users to see the individual tickets and assign them to specific users. The default value is **Public** which means that every user of the current account can access the ticket. It is also possible to either assign a ticket to administrator users only, or to an individual user.

The screenshot shows the 'Licenses' section of the Vizrt Admin interface. It features a search bar and a table of tickets. The table has the following columns: Ticket, Licenses, Type, and Owner. The 'Owner' column for all tickets is set to 'Public (Every Member of this group)'. The table contains 10 entries, with a 'Showing 1 to 10 of 174 entries' indicator at the bottom.

| Ticket | Licenses | Type | Owner |
|-------------------------------|--|--------|-------------------------------------|
| 27FGC-7K83E-BAVSM-792K6-DV22 | Expiration Time - Viz Engine Im1 - Combination Feature Frameserver - ... | Public | Public (Every Member of this group) |
| 29GW2-B7RUU-SUQ9P-UMPEP-U63UB | Permanent - Viz Engine Im1 - Combination Feature Frameserver - ... | Public | Public (Every Member of this group) |
| 2A2W7-NVQFN-E79K2-5HVQY-BB36E | Expiration Time - Viz Engine Im1 - Combination Feature Frameserver - ... | Public | Public (Every Member of this group) |
| 2AE4T-CC29S-4QK3U-68VZ5-FM93W | Viz Arena Im1 - 4K Resolution (Add-on) - (Network), ... | Public | Public (Every Member of this group) |
| 2AT6D-TSX9P-2THYA-U6MDQ-3B6RL | Viz Engine Im1 - 4K Video Enablement - (Network), ... | Public | Public (Every Member of this group) |
| 2EWUR-TT4JA-BT69L-DCQ2W-NVU93 | Expiration Time - Viz Engine Im1 - Preview Core - (Local), ... | Public | Public (Every Member of this group) |
| 2MWVY-7QBPF-2EFBL-FHGD-R8C35 | Expiration Time - Viz Engine Im1 - Preview Core - (Local), ... | Public | Public (Every Member of this group) |
| 2WCFK-3265Y-ALSQC-627FR-N7YZ6 | Viz Engine Im1 - 4K Video Enablement - (Network), ... | Public | Public (Every Member of this group) |
| 2YR0G-3C76G-UDG9K-93L2W-HS9G4 | Permanent - Viz Engine Im1 - Combination Feature Frameserver - ... | Public | Public (Every Member of this group) |
| 2ZNS2-YLPMG-KGD8C-W9LLQ-8H8MG | Viz Engine Im1 - 4K Video Enablement - (Network), ... | Public | Public (Every Member of this group) |

Tip: Tickets are only shown in the licenses page of a user if the access permission is set to public or the ticket has been assigned to the individual user.

4.7.4 Users

In this section you can see which users are connected to the account. In addition to the email address, the user logged into the license portal, has its permissions displayed.

The screenshot shows the 'Users' section of the Vizrt Admin interface. It features a search bar with the text 'bpa' and a table of users. The table has the following columns: Email Address, Roles, Created, and CmCloudContainer. The 'Roles' column for the user 'bpa@vizrt.com' lists 'admin, Wibu_Admin, Wibu_SmartBindLoose, Wibu_Rehost, Wibu_Artist_Free, Wibu_SF_User'. There is a 'Get Credential File' button next to the user entry. The table shows 'Showing 1 to 1 of 1 entries (filtered from 11 total entries)'.

| Email Address | Roles | Created | CmCloudContainer |
|---------------|---|------------|---------------------|
| bpa@vizrt.com | admin, Wibu_Admin, Wibu_SmartBindLoose, Wibu_Rehost, Wibu_Artist_Free, Wibu_SF_User | 2024-03-13 | Get Credential File |

Info: The **CmCloudContainer** column and the **Get Credential File** button are not currently used, and are part of upcoming features of the Licensing Portal.

4.7.5 Customers

The customers section displays the child accounts of the current account. Clicking the **Show** button forwards to the Admin Page of the child account and provides the same functionality as described in the [Admin Page](#).

Reseller - Vizrt Company (ISV)

Information

Licenses

Tickets

Users

Customers

Show 10 entries

Search: MyChannel


| Name | Description |
|-----------|-------------|
| Mychannel | Mychannel |

Showing 1 to 1 of 1 entries (filtered from 12,521 total entries)

Previous 1 Next


4.8 Customers

The customers section displays the child accounts of the current account. Clicking the **Show** button forwards to the Admin Page of the child account and provides the same functionality as described in the [Admin Page](#).




4.9 Account

To access the account information, click on the portrait symbol on the top right of the license portal.



Clicking this button, either forwards to the account information, or provides the option to log out of the license portal.

The account information provides all of the information about the user and account data:



| Your Data | Description |
|---------------|--|
| Email Address | Email address of the current user. |
| Name | Account ID of the account the user is assigned to. |
| Description | Account name of the account the user is assigned to. |

| Your Data | Description |
|--------------------------------|---|
| Registered since | Date of creation of the current user. |
| Download | Description |
| CodeMeter Runtime | WIBUs CodeMeter Runtime is required to run any Vizrt Software Product. Also required to run a license server. This installer is also shipped with all Vizrt Software bundles. |
| Viz Artist | Downloader for Viz Free Artist. |
| Vizrt Offline Licensing Helper | This tool is required for offline licensing activation. Please only use to create a container in case there is none on the machine. The other steps of the offline activation can be done like described here . |

4.10 Re-Hosting

Info: The Re-hosting feature currently requires more computations. Hence, you might see a delay of a few minutes while performing this action. Please do not refresh the browser window.

With Re-Hosting, you can rehost an already activated license from a Dongle or Software Container back to the license portal. This enables flexibility in license usage and provides the option to move licenses between locations.

Re-Hosting licenses follows the same procedure as the license activation process and it allows [online](#) and [offline](#) workflow.

It is required to have an additional permission that can be requested from Vizrt for individual users.

If a user has the Re-Host permission enabled, a button is displayed below the licenses table on the [Licenses](#) page:

The screenshot shows the Vizrt Licenses page. At the top, there are navigation tabs: Customers, Admin, Licenses, Containers, and Free Licenses. Below the navigation, there is a search bar and a 'Show 10 entries' dropdown. The main content is a table with the following columns: Ticket, Name, Order ID, QTY, End Date, Activated On, Container, and Status. The table is divided into two sections by expandable headers: '4V63S-2M97P-8BAS2-U373C-LGQ6C (5)' and 'B4EW6-KH694-N279S-7RY33-U226H (5)'. The first section contains five rows of licenses, and the second section contains five rows. At the bottom of the page, there are two buttons: 'Activate Licenses' and 'Re-Host Licenses'. The 'Re-Host Licenses' button is highlighted with a red box.

| Ticket | Name | Order ID | QTY | End Date | Activated On | Container | Status |
|-----------------------------------|---|----------|-----|------------|--------------|----------------|-----------|
| 4V63S-2M97P-8BAS2-U373C-LGQ6C (5) | | | | | | | |
| 4V63S-2M97P-8BAS2-U373C-LGQ6C | V3 TriCaster Now - TriCaster Now Bridge - (Network) | | 4 | 2025-01-25 | - | | Available |
| 4V63S-2M97P-8BAS2-U373C-LGQ6C | V3 Viz Arena - Developer Features - (Network) | | 3 | 2090-12-31 | - | | Available |
| 4V63S-2M97P-8BAS2-U373C-LGQ6C | V3 Viz Engine - Artist Preview - (Network) | | 9 | 2025-01-30 | - | | Available |
| 4V63S-2M97P-8BAS2-U373C-LGQ6C | V3 TriCaster Now - TriCaster Now Bridge - (Network) | | 1 | 2025-01-25 | - | | Available |
| 4V63S-2M97P-8BAS2-U373C-LGQ6C | V3 Viz Arena - Developer Features - (Network) | | 2 | 2090-12-31 | 2024-03-05 | 130-2925769937 | Activated |
| B4EW6-KH694-N279S-7RY33-U226H (5) | | | | | | | |
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - 4K Video Enablement - (Network) | | 1 | 2025-03-01 | 2024-03-21 | 130-1540195032 | Activated |
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - Artist - (Network) | | 1 | 2025-03-01 | 2024-03-21 | 130-1540195032 | Activated |
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - Artist Preview - (Network) | | 1 | 2025-03-01 | 2024-03-21 | 130-1540195032 | Activated |
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - Bone&Skin Live Motion Capture - (Network) | | 1 | 2025-03-01 | 2024-03-21 | 130-1540195032 | Activated |
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - Chroma FX - (Network) | | 1 | 2025-03-01 | 2024-03-04 | 130-3874608740 | Activated |

Showing 1 to 10 of 151 entries (filtered from 163 total entries)


Activate Licenses Re-Host Licenses

After clicking the **Re-Host Licenses** button, a list of licenses available for rehost is displayed. When using the offline version, the portal first redirects the interface to select the Dongle or Software Container the license should be rehosted from.

The screenshot shows the 'Re-Hostable Licenses - Select CmContainer' page. At the top, there is a navigation bar with 'Customers', 'Admin', 'Licenses', 'Containers', and 'Free Licenses'. Below the navigation bar, a message states: 'Several CmContainers with re-hostable license were found. Please select the desired CmContainer.' The main content area displays four license entries, each with a document icon, a license ID, and a list of features:

- License 130-2925769937:**
 - Re-Hostable Licenses:
 - V3 Viz Arena (Network)
 - Developer Features - 4V63S-2M97P-8BAS2-U373C-LGQ6C
- License 130-1540195032:**
 - Re-Hostable Licenses:
 - Viz Engine lmi1 (Network)
 - Artist - B4EW6-KH694-N279S-7RY33-U226H
 - Combination Feature - B4EW6-KH694-N279S-7RY33-U226H
 - Combination Feature DVI - B4EW6-KH694-N279S-7RY33-U226H
 - Combination Feature MoxZIP - B4EW6-KH694-N279S-7RY33-U226H
 - Combination Feature ND1 - B4EW6-KH694-N279S-7RY33-U226H
 - Engine Core - B4EW6-KH694-N279S-7RY33-U226H
 - SDI/IP OUT Channel - B4EW6-KH694-N279S-7RY33-U226H
 - SDI/IP Video Input Enablement - B4EW6-KH694-N279S-7RY33-U226H
 - Service Host Core - B4EW6-KH694-N279S-7RY33-U226H
 - Viz Engine lmi1 (Local)
 - Combination Feature Frameserver- (Network) - B4EW6-KH694-N279S-7RY33-U226H
 - Viz Engine lmi1 (Local)
 - Combination Feature Frameserver- (Network) - B4EW6-KH694-N279S-7RY33-U226H
- License 130-3874608740:**
 - Re-Hostable Licenses:
 - Viz Engine lmi1 (Network)
 - Chroma FX - B4EW6-KH694-N279S-7RY33-U226H
- License 3-4589751:**
 - Re-Hostable Licenses:
 - V3 Media Sequencer Engine (Network)
 - MSE Core - FAB5N-CK55V-4PYX8-GSC23-XWBA7

In the online version, the portal directs to the view below, where it is possible to select the features that should be rehosted.

 **Tip:** In this view it is possible to switch to the offline workflow by clicking on **File-based license transfer** on the lower right corner. Follow the same instructions as for the **offline license activation**.

vizrt
Customers | Admin | Licenses | Containers | Free Licenses

Re-Hostable Licenses

To re-host licenses from one CmContainer to another CmContainer:

1. Make sure that the CmContainer with Serial **130-1540195032** is connected to this computer. If this CmContainer is not connected to this computer, connect it now and click "Rescan for CmContainers".
2. Select the licenses you want to re-host.
3. Click "Re-Host Selected Licenses Now".
4. After the successful deactivation of the selected licenses, you can activate them again in another CmContainer.

| <input type="checkbox"/> Ticket | Name | Activated On | Container | Status |
|--|---|---------------------|----------------|-----------|
| <input type="checkbox"/> B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - Artist - (Network) <small>(License Quantity: 1)</small> | 2024-03-21 14:25:17 | 130-1540195032 | Activated |
| <input type="checkbox"/> B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - Combination Feature - (Network) <small>(License Quantity: 1)</small> | 2024-03-21 14:25:17 | 130-1540195032 | Activated |
| <input type="checkbox"/> B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - Combination Feature DVI - (Network) <small>(License Quantity: 1)</small> | 2024-03-21 14:25:17 | 130-1540195032 | Activated |
| <input type="checkbox"/> B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - Combination Feature Frameserver- (Network) <small>(License Quantity: 1)</small> | 2024-03-21 14:25:17 | 130-1540195032 | Activated |
| <input type="checkbox"/> B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - Combination Feature MezzIP - (Network) <small>(License Quantity: 1)</small> | 2024-03-21 14:25:17 | 130-1540195032 | Activated |
| <input type="checkbox"/> B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - Combination Feature NDI - (Network) <small>(License Quantity: 1)</small> | 2024-03-21 14:25:17 | 130-1540195032 | Activated |
| <input type="checkbox"/> B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - Engine Core - (Network) <small>(License Quantity: 1)</small> | 2024-03-21 14:25:17 | 130-1540195032 | Activated |
| <input type="checkbox"/> B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - SDI/IP OUT Channel - (Network) <small>(License Quantity: 1)</small> | 2024-03-21 14:25:17 | 130-1540195032 | Activated |
| <input type="checkbox"/> B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - SDI/IP Video Input Enablement - (Network) <small>(License Quantity: 1)</small> | 2024-03-21 14:25:17 | 130-1540195032 | Activated |
| <input type="checkbox"/> B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - Service Host Core - (Network) <small>(License Quantity: 1)</small> | 2024-03-21 14:25:17 | 130-1540195032 | Activated |

Next
File-based license transfer

- + Show other licenses
- + Select CmContainer
- + Licenses

Once selected, the available features to rehost are shown. Select the ones that need to be rehosted and click **Next**.

In the next interface the activation summary is displayed, stating the licenses that are moved from the Dongle or Software Container back to the License Portal.

vizrt
Customers | Admin | Licenses Containers | Free Licenses

License Update

Licenses to be added

| Ticket | Name | End Date | Activated On | Container | Status |
|--------|------|----------|--------------|-----------|--------|
|--------|------|----------|--------------|-----------|--------|

Licenses to be changed

| Ticket | Name | End Date | Activated On | Container | Status |
|--------|------|----------|--------------|-----------|--------|
|--------|------|----------|--------------|-----------|--------|

Licenses to be removed

| Ticket | Name | End Date | Activated On | Container | Status |
|-------------------------------|---|------------|---------------------|----------------|-----------|
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine Imit1 - Artist - (Network) <small>(License Quantity: 1)</small> | 2024-02-29 | 2024-03-21 14:25:17 | 130-1540195032 | Activated |
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine Imit1 - Combination Feature - (Network) <small>(License Quantity: 1)</small> | 2024-02-29 | 2024-03-21 14:25:17 | 130-1540195032 | Activated |
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine Imit1 - Combination Feature DVI - (Network) <small>(License Quantity: 1)</small> | 2024-02-29 | 2024-03-21 14:25:17 | 130-1540195032 | Activated |
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine Imit1 - Combination Feature Frameserver - (Network) <small>(License Quantity: 1)</small> | 2024-02-29 | 2024-03-21 14:25:17 | 130-1540195032 | Activated |
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine Imit1 - Combination Feature MezzIP - (Network) <small>(License Quantity: 1)</small> | 2024-02-29 | 2024-03-21 14:25:17 | 130-1540195032 | Activated |
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine Imit1 - Combination Feature NDI - (Network) <small>(License Quantity: 1)</small> | 2024-02-29 | 2024-03-21 14:25:17 | 130-1540195032 | Activated |
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine Imit1 - Engine Core - (Network) <small>(License Quantity: 1)</small> | 2024-02-29 | 2024-03-21 14:25:17 | 130-1540195032 | Activated |
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine Imit1 - SDI/IP OUT Channel - (Network) <small>(License Quantity: 1)</small> | 2024-02-29 | 2024-03-21 14:25:17 | 130-1540195032 | Activated |
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine Imit1 - SDI/IP Video Input Enablement - (Network) <small>(License Quantity: 1)</small> | 2024-02-29 | 2024-03-21 14:25:17 | 130-1540195032 | Activated |
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine Imit1 - Service Host Core - (Network) <small>(License Quantity: 1)</small> | 2024-02-29 | 2024-03-21 14:25:17 | 130-1540195032 | Activated |

Re-Host Selected Licenses Now

Warning: Re-Hosting will always remove the full quantity of a license feature from a Dongle or Software Container.

Click on **Re-Host Selected Licenses Now** to start the process.
 Once finished, a short message is displayed and the portal continues to the [license page](#).

Online License Transfer

Starting license transfer.
 Downloading license update.
 Importing license update to CmContainer.
 Creating receipt.
 Uploading receipt.


License transfer completed successfully!

OK

5 CodeMeter WebAdmin


The CodeMeter WebAdmin is the user interface of the WIBU CodeMeter Runtime. It is used to manage local settings, review available licenses, setup a license server and troubleshooting. The WIBU CodeMeter Runtime is shipped with all Vizrt Software products and is also available for download in the [account tab](#) of the license portal.

To access the WebAdmin, open the CodeMeter ControlCenter and click on the **WebAdmin** button in the lower right corner.



Alternatively, the CodeMeter WebAdmin is accessible via URL: <http://localhost:22352/dashboard.html>.

Info: To access the WebAdmin of a remote computer, replace the localhost in the URL <http://localhost:22352/dashboard.html> with the IP address or the hostname of the remote computer. Please note that accessing the CodeMeter WebAdmin remotely needs to be enabled.




In the top menu bar of the CodeMeter WebAdmin, you have access to different information and settings, and the option to select a language. Clicking the question mark, opens WIBUs documentation and information about the exact page that is currently displayed in CodeMeter

WebAdmin.

The **W** symbol provides information regarding the connection. If it is Read-Only (**R**) or has permission to perform changes (**W**).

You can change between CodeMeter WebAdmins that are known to the network. To do so, select the **Current Server** option on the bottom bar of the page:



After scanning the network for available servers, the options are displayed, showing the hostname and IP address.

By clicking on the server and if the access is enabled, the page is forwarded to the CodeMeter WebAdmin of the server.

5.1 Configuration

The Configuration tab is used to configure settings for clients and network servers.

There are three main sections available: Basic, Server and Advanced. They can be selected by hovering over the Configuration tab.

Tip: For a more detailed description, click the question mark on top of the page to see the CodeMeter User Help.

- [Basic Configuration](#)
 - [Server Search List](#)
 - [Proxy](#)
 - [WebAdmin](#)
 - [Backup](#)
- [Server](#)
 - [Server Access](#)
 - [License Access Permissions](#)
 - [License Transfer Configuration](#)
- [Advanced](#)
 - [CodeMeter Time Server](#)
 - [Trusted WebSocket Origins](#)
 - [Extra](#)

5.1.1 Basic Configuration

Server Search List

The Server Search List is used to configure a connection to a license server on a client.

The screenshot displays the CodeMeter WebAdmin interface. The top navigation bar includes the WJIBU SYSTEMS logo, the title 'CodeMeter WebAdmin', and a user profile icon. Below the navigation bar, a teal header contains the main menu items: Dashboard, Container, License Monitoring, Diagnosis, Configuration (selected), and Info. Under the Configuration menu, there are sub-menus for Basic Configuration, Server Search List (selected), Proxy, WebAdmin, and Backup. The main content area shows the 'Server Search List' configuration page. It features a list of server entries, currently containing one entry: '1. Automatic server search (255.255.255.255)'. Below the list is a '+ add new Server' button. At the bottom of the configuration area are 'Apply' and 'Restore Defaults' buttons. To the right of the configuration area is a circular icon representing two server racks connected by a line.

To add a new server to the list, click **add new Server** and provide the hostname or IP address of the license server.

When there are multiple servers added, it is possible to change the order. Per default, Vizrt Software products always check for available licenses on the first server in the list, before moving to the other servers.

Proxy

In this section the proxy preference can be selected.



WebAdmin

In the WebAdmin configuration, you can enable the read access to the CodeMeter WebAdmin from an external computer within the network range. In addition, it is possible to select the preferred protocol and authentication.

CodeMeter WebAdmin

Dashboard Container License Monitoring Diagnosis Configuration Info

Basic Configuration WebAdmin

Server Search List Proxy WebAdmin Backup

Remote Read Access

- Allow
- Deny

Changes require restart of the CmWebAdmin service

Protocol Selection

- HTTP (sets authentication to none)
- HTTPS (with automatically created self-signed certificate)
- HTTPS (with custom certificate)

Required Authentication


- None (No remote write access possible!)
- Write Access (requires HTTPS)
- Read and Write Access (requires HTTPS)

Apply Restore Defaults

Tip: It is recommended to allow the **Remote Read Access** on license servers at all times, to ensure clients can connect safely.

Backup


This option allows to define a backup for Dongle and Software Container data.



5.1.2 Server


Server Access

The Server Access is the main setting required to run a license server. This setting needs to be enabled to allow clients to connect to the license server and access licenses.



License Access Permissions

The License Access Permissions allows access to rules for licenses. It is possible to reserve licenses for specified clients using the IP address of the client. Reserved licenses on the server cannot be accessed by other clients.




The screenshot displays the CodeMeter WebAdmin interface. The top navigation bar includes 'Dashboard', 'Container', 'License Monitoring', 'Diagnosis', 'Configuration', and 'Info'. The 'Configuration' menu is expanded, showing 'Server Configuration' and 'License Access Permissions'. The 'License Access Permissions' page is active, with tabs for 'Server Access', 'License Access Permissions', and 'License Transfer Configuration'. The 'Mode' section has two radio buttons: 'Basic' (selected) and 'Advanced'. Below this, a message states: 'CodeMeter Server is currently running in License Access Permission Mode: **Basic**'. The 'Basic Mode Configuration' section contains a 'Clients' list (empty), 'Add' and 'Remove' buttons, and an 'Enable FSB Access' checkbox. At the bottom, there are 'Apply', 'Undo Changes', and 'Restore Defaults' buttons. A large teal circular icon with a white document and person symbol is on the right side of the configuration area.

License Transfer Configuration

In this section the license transfer can be configured.


Warning: This is a functionality Vizrt currently does not support.



5.1.3 Advanced


CodeMeter Time Server

Here you can select the CodeMeter Time Server.




Trusted WebSocket Origins

This section is used to add trusted WebSocket Origins if required.




Extra

Extra is for additional configuration like the preferred **API-Communication-Mode** or **Advanced Network** settings.



CodeMeter WebAdmin



Dashboard Container ▾ License Monitoring ▾ Diagnosis ▾ Configuration ▾ Info

⚙️ Advanced Configuration
Extra
W
?
🇺🇸 English (US) ▾

CodeMeter Time Server
Trusted WebSocket Origins
Extra

API-Communication-Mode

- IPv4
- IPv6
- Shared Memory

Edit

Changes require restart of the CodeMeter service

Network Advanced

Network Port:

Network Timeout: Seconds

UDP Waiting Time: Milliseconds

Edit

Changes require restart of the CodeMeter service

License Transfer Configuration

Storage of additional License Transfer information: Days

Edit


Changes require restart of the CodeMeter service

Additional WebAdmin Configuration

Enable Prepared License Borrowing Configuration

Prepared License Borrowing is supported for Firm Codes smaller than 6,000,000.

Edit



⚠️ **Warning:** License Transfer and Prepared License Borrowing is currently not supported by Vizrt.

5.2 Container

The containers tab displays all locally connected dongles or Software Containers. It is possible to have multiple Software Containers or dongles connected to one system.

The screenshot shows the CodeMeter WebAdmin interface. The top navigation bar includes 'Dashboard', 'Container', 'License Monitoring', 'Diagnosis', 'Configuration', and 'Info'. The 'Container' tab is selected, showing a list of three containers. Each container entry includes a 'Universal Firm Code CmActLicense' number, a unique ID (e.g., 130-17953368), and the license type 'CmActLicense/UFC 3.00'. Below each entry are expandable sections for 'Licenses', 'CmContainer Info', and 'User Data'.

To access the content of a dongle or Software Container, click on the container to open it.

This screenshot shows the detailed view of a container. The breadcrumb navigation indicates the path: 'All Container > Universal Firm Code CmActLicense 6000203 (130-17953368)'. The main content area displays the container's details and a table of licenses. The license table has columns for 'Product Code', 'Name', 'Unit Counter', 'Valid Until', 'License Quantity', and 'Feature Map'. One license is listed with Product Code '1300000' and Name 'Viz Graphic Hub - Viz Graphic Hub'.

| Product Code | Name | Unit Counter | Valid Until | License Quantity | Feature Map |
|--------------|-----------------------------------|--------------|---------------------|------------------|-------------|
| 1300000 | Viz Graphic Hub - Viz Graphic Hub | n/a | 2024-03-31 23:59:47 | 1 | 0x6 |

The available licenses, including expiration date and license quantity are displayed. Clicking on the **Product Code** in front of the feature name, shows the **Product Item Details**.

The screenshot shows the CodeMeter WebAdmin interface. The top navigation bar includes 'Dashboard', 'Container', 'License Monitoring', 'Diagnosis', 'Configuration', and 'Info'. The breadcrumb trail indicates the path: 'All Container' > 'Universal Firm Code CmActLicense 6000203 (130-17953368)' > 'Firm Code 6000203' > 'Product Code 1300000'. The main content area is titled 'Product Item Details' and shows information for 'Product Item 6000203:1300000 of CmContainer "Universal Firm Code CmActLicense 6000203" (130-17953368)'. Below this is a table with the following data:

| Product Item Options | Size (Bytes) | Dependencies | Value |
|------------------------------|--------------|-----------------------|---|
| Text | 33 | | Viz Graphic Hub - Viz Graphic Hub |
| Feature Map | 4 | data, serial, counter | 0000 0000 0000 0000 0000 0000 0000 0110 (0x6) |
| Expiration Time | 4 | data, serial, counter | 2024-03-31 23:59:47 |
| License Quantity | 4 | data, serial, counter | 1 |
| Protected Data | 22 | data, serial, counter | 0x6c 0x69 0x63 0x65 0x6e 0x73 0x65 0x61 0x63 0x63 0x65 0x73 0x73 0x74 0x79 0x70 0x65 0x3d 0x35 0x31 0x32 0x3b |
| Maintenance Period | 8 | data, serial, counter | Start: 2000-01-02 00:59:59 End: 2025-04-02 01:59:59 |
| Extended Protected Data #0 | 30 | data, serial, counter | 0x00 0x00 0x00 0x1a 0x00 0x01 0x00 0x04 0x00 0x01 0x00 0x03 0x00 0x04 0x00 0x06 0x00 0x03 0x00 0x01 0x00 0x01 0x00 0x07 0x00 0x04 0x00 0x00 0x02 0x00 |
| Extended Protected Data #136 | 16 | data, serial, counter | 0x6c 0x63 0x64 0x63 0x00 0x01 0xce 0xfc 0x14 0x00 0x00 0x00 0x00 0x00 0x01 0x00 |

The **Product Item Details** display information about the license. The most relevant are **Expiration Time**, **License Quantity** and the current **Maintenance Period** of the license.

Info: The Maintenance Period on the dongle or Software Container can be different to the one that is set in the license portal. If a newer Maintenance Period is available in the License Portal, the local license on Dongles or Software Containers can be updated.

5.3 Dashboard

The Dashboard is the landing page of CodeMeter WebAdmin. It displays a short overview of the current system as well as the sessions that are currently connected.

The screenshot shows the CodeMeter WebAdmin interface. At the top left is the WJIBU SYSTEMS logo. The main title is 'CodeMeter WebAdmin'. Below the title is a navigation bar with 'Dashboard' selected, and other options: 'Container', 'License Monitoring', 'Diagnosis', 'Configuration', and 'Info'. There are also icons for a refresh button, a help button, and a language dropdown set to 'English (US)'. The main content area is divided into two panels. The left panel displays system information: Current Server (license-server), IP address (redacted), Operating System (Windows Server 2022), Server Startup (2023-10-31 16:54:05), Server Version (Version 7.60d of 13. October 2023 (Build 5638)), and Runtime Version (7.60d). The right panel is titled 'Sessions (916)' and shows a table of active sessions. The table has three columns: a redacted column, a column with values '6000203 : 3000000', and a column with values 'Data Center - D ata Center Core'. There are three rows of data shown, with a scrollbar on the right indicating more sessions are present.

Info: The sessions window is only displayed when clients actively acquire licenses. More information about the sessions can be found in the [License Monitoring](#).

5.4 Diagnosis

The Diagnosis page displays the event log of the WIBU Runtime.


The screenshot shows the CodeMeter WebAdmin interface. At the top, there is a navigation bar with the following tabs: Dashboard, Container, License Monitoring, **Diagnosis**, Configuration, and Info. Below the navigation bar, there is a sub-menu with 'Events' selected. The main content area displays a list of events in a scrollable window. The events include:

- 2024-03-21 09:33:13: API Error 200 (ENTRY NOT FOUND) occurred!
- 2024-03-21 09:33:20: Entry (3-4587862 6000203:0) not found - Event WB0200 (ENTRY NOT FOUND), Request IP-Address(NT AUTHORITY\LOCAL SERVICE) with UserLimit
- 2024-03-21 09:33:20: API Error 200 (ENTRY NOT FOUND) occurred!
- 2024-03-21 09:33:25: Access over LAN from to FC:PC=6000203:1200000 with NoUserLimit (Handle 2319)
- 2024-03-21 09:33:25: Handle 2319 released
- 2024-03-21 09:33:28: Access over LAN from (SID 0xc03d / 0x00) to FC:PC=6000203:1200000 RD=2024-02-07 with StationShare Mode (Handle 754)
- 2024-03-21 09:33:41: Access over LAN from to FC:PC=6000203:1200000 with NoUserLimit (Handle 1958)
- 2024-03-21 09:33:41: Handle 1958 released
- 2024-03-21 09:34:07: Access from SubSystem (Handle 2582)
- 2024-03-21 09:34:08: Handle 2582 released
- 2024-03-21 09:34:08: Access over LAN from to SubSystem (Handle 665)
- 2024-03-21 09:34:08: Handle 665 released
- 2024-03-21 09:34:24: Handle 2628 released
- 2024-03-21 09:34:24: Handle 2152 released
- 2024-03-21 09:34:24: Handle 263 released
- 2024-03-21 09:34:24: Handle 904 released
- 2024-03-21 09:34:24: Handle 1222 released
- 2024-03-21 09:34:24: Handle 2523 released
- 2024-03-21 09:34:24: Handle 608 released
- 2024-03-21 09:34:24: Handle 2810 released
- 2024-03-21 09:34:24: Handle 893 released
- 2024-03-21 09:34:24: Handle 2698 released
- 2024-03-21 09:34:24: Handle 2006 released
- 2024-03-21 09:34:24: Handle 1902 released
- 2024-03-21 09:34:24: Handle 2739 released
- 2024-03-21 09:34:24: Handle 2891 released
- 2024-03-21 09:34:24: Handle 1862 released
- 2024-03-21 09:34:24: Handle 974 released
- 2024-03-21 09:34:24: Handle 2784 released
- 2024-03-21 09:34:24: Handle 844 released
- 2024-03-21 09:34:24: Handle 1040 released
- 2024-03-21 09:34:24: Handle 374 released
- 2024-03-21 09:34:24: Handle 466 released
- 2024-03-21 09:34:24: Handle 1536 released
- 2024-03-21 09:34:24: Handle 1734 released
- 2024-03-21 09:34:24: Handle 1572 released
- 2024-03-21 09:34:24: Handle 2900 released
- 2024-03-21 09:34:24: Handle 1780 released
- 2024-03-21 09:34:24: Handle 1914 released
- 2024-03-21 09:34:24: Handle 1406 released
- 2024-03-21 09:34:24: Handle 2327 released
- 2024-03-21 09:34:24: Handle 2579 released
- 2024-03-21 09:34:24: Handle 271 released
- 2024-03-21 09:34:24: Handle 2852 released
- 2024-03-21 09:34:24: Handle 1443 released
- 2024-03-21 09:34:49: Entry (130-755289660 6000203:3000000 RD=2022-06-15) not found - Event WB0200 (ENTRY NOT FOUND), Request IP-Address
- 2024-03-21 09:34:49: Entry (130-755289660 6000203:3000000 RD=2022-06-15) not found - Event WB0200 (ENTRY NOT FOUND), Request IP-Address
- 2024-03-21 09:34:49: API Error 200 (ENTRY NOT FOUND) occurred!
- 2024-03-21 09:35:13: Entry (3-3695087 6000203:3000000 RD=2024-03-18) not found - Event WB0200 (ENTRY NOT FOUND), Request IP-Address(NT AUTHORITY\LOCAL SERVICE) (SID 0x1234 / 0x00) with StationShare Mode
- 2024-03-21 09:35:13: API Error 200 (ENTRY NOT FOUND) occurred!
- 2024-03-21 09:35:22: Entry (3-4587862 6000203:0) not found - Event WB0200 (ENTRY NOT FOUND), Request IP-Address(NT AUTHORITY\LOCAL SERVICE) with UserLimit
- 2024-03-21 09:35:22: API Error 200 (ENTRY NOT FOUND) occurred!
- 2024-03-21 09:35:37: Handle 1479 released
- 2024-03-21 09:35:39: Handle 2139 released
- 2024-03-21 09:35:39: Access from to SubSystem (Handle 1474)
- 2024-03-21 09:35:39: Handle 754 released
- 2024-03-21 09:35:40: Handle 1474 released
- 2024-03-21 09:35:40: Access over LAN from to SubSystem (Handle 95)
- 2024-03-21 09:35:41: Handle 95 released

At the bottom of the interface, there is a status bar showing 'Current Server: license-server (.....)' and 'WebAdmin Version: 7.60'.

5.4.1 CmDust Log Export


To export the log into a text file, open the Windows Search on the local machine of the CodeMeter WebAdmin and search for the CmDust application. Running this application collects all of the data from CodeMeter Runtime into a text file.

 **Info:** The CmDust application needs to be executed on the machine the Wibu Runtime is installed. This means that it needs to be executed on the license server directly in a license server workflow, or locally on a client when working with local dongles or Software Containers.

5.5 License Monitor

License Monitoring is used to monitor the usage of licenses on a license server. There are two different sections which can be selected by hovering the mouse over License Monitoring: **All Licenses** and **Sessions**.

5.5.1 All Licenses



The screenshot shows the CodeMeter WebAdmin interface. The top navigation bar includes 'Dashboard', 'Container', 'License Monitoring', 'Diagnosis', 'Configuration', and 'Info'. The 'License Monitoring' section is active, and the 'All Licenses' sub-section is selected. The main content area is titled 'Available Licenses on 'license-server2'' and shows a table of licenses for '6000203 Vizrt Austria GmbH'.

| Product Code | Name | Feature Map | License Quantity | Used | Available |
|--------------|---|-------------|------------------|------|-----------|
| 230001 | Viz Pilot - Connection Broker | 0x6 | 101 | 0 | 101 |
| 1300000 | Viz Graphic Hub - Viz Graphic Hub | 0x6 | 100 | 3 | 97 |
| 130100 | Viz Graphic Hub - Graphic Hub Image Library extension | 0x6 | 100 | 1 | 99 |
| 230000 | Viz Pilot - Viz Pilot Server | 0x6 | 100 | 0 | 100 |
| 230100 | Viz Pilot - Template Builder | 0x6 | 100 | 0 | 100 |
| 230200 | Viz Pilot - Viz Pilot Server replication | 0x6 | 100 | 0 | 100 |
| 230300 | Viz Pilot - Pilot Edge | 0x6 | 100 | 0 | 100 |
| 230301 | Viz Pilot - NLE | 0x6 | 100 | 0 | 100 |
| 1200000 | Viz Engine - Engine Core | 0x6 | 100 | 0 | 100 |
| 1200001 | Viz Engine - Preview Core | 0x6 | 100 | 0 | 100 |
| 1200003 | Viz Engine - Ingest Core | 0x6 | 100 | 0 | 100 |
| 1200004 | Viz Engine - Service Host Core | 0x6 | 100 | 0 | 100 |
| 1200100 | Viz Engine - Combination Feature | 0x6 | 100 | 0 | 100 |
| 1200101 | Viz Engine - Artist | 0x6 | 100 | 0 | 100 |
| 1200102 | Viz Engine - Artist Preview | 0x6 | 100 | 0 | 100 |

The License Monitoring page shows the total License Quantity and the usage.

Clicking on the **Product Code**, shows the **License Monitoring Details** page where the exact users of the selected feature are displayed.

CodeMeter WebAdmin

Dashboard Container License Monitoring Diagnosis Configuration Info

All Licenses license-server2 (3-3695087) - Entry6000203:1300000 (0x6) English (US)

License Monitoring Details

| CmContainer | Entry | Available | Total |
|-----------------------------|-----------------------|-----------|-------|
| license-server2 (3-3695087) | 6000203:1300000 (0x6) | 97 | 100 |

| ID | Client (User) | Client Process ID | Application Information | Access Mode | First Access | Last Access | Expires | Action |
|------|-------------------------------|-------------------|-------------------------|-------------|---------------------|---------------------|---------|--------|
| 404 | XXXXXXXXXX (SYSTEM) | 0 | | Exclusive | 2024-02-15 11:58:09 | 2024-03-21 10:35:49 | | ⊘ |
| 851 | XXXXXXXXXX (WORKGROUP\SYSTEM) | 0 | | Exclusive | 2024-03-18 12:17:52 | 2024-03-21 10:35:42 | | ⊘ |
| 1210 | XXXXXXXXXX (SYSTEM) | 0 | | Exclusive | 2024-02-28 16:47:05 | 2024-03-21 10:35:10 | | ⊘ |

Info: The **Action** column allows you to terminate a connection of a client to that specific license item, and must be used with care.

5.5.2 Sessions

The sessions section shows the details about the total clients connected to a license server, and is mostly used for information.

CodeMeter WebAdmin

Dashboard Container License Monitoring Diagnosis Configuration Info

Sessions

| Client | CmContainer | Firm Item | Product Item | Access Mode |
|--------|-----------------------------|----------------------------------|--|---------------|
| | license-server2 (3-3695087) | 6000203 : Vizrt Austria Gm bH | 2200300 : Media Sequencer Engine - MSE PilotEdge | Station Share |
| | license-server2 (3-3695087) | 6000203 : Vizrt Austria Gm bH | 2200000 : Media Sequencer Engine - MSE Core | Station Share |
| | license-server2 (3-3695087) | 6000203 : Vizrt Austria Gm bH | 2200000 : Media Sequencer Engine - MSE Core | Station Share |
| | license-server2 (3-3695087) | 6000203 : Vizrt Austria Gm bH | 2200000 : Media Sequencer Engine - MSE Core | Station Share |
| | license-server2 (3-3695087) | 6000203 : Vizrt Austria Gm bH | 2200000 : Media Sequencer Engine - MSE Core | Station Share |
| | license-server2 (3-3695087) | 6000203 : Vizrt Austria Gm bH | 2200000 : Media Sequencer Engine - MSE Core | Station Share |
| | license-server2 (3-3695087) | 6000203 : Vizrt Austria Gm bH | 1300000 : Viz Graphic Hub - Viz Graphic Hub | Exclusive |
| | license-server2 (3-3695087) | 6000203 : Vizrt Austria Gm bH | 1300000 : Viz Graphic Hub - Viz Graphic Hub | Exclusive |
| | license-server2 (3-3695087) | 6000203 : Vizrt Austria Gm bH | 1300000 : Viz Graphic Hub - Viz Graphic Hub | Exclusive |
| | license-server2 (3-3695087) | 6000203 : Vizrt Austria Gm bH | 130100 : Viz Graphic Hub - Graphic Hub Image Library exte nslon | User Limit |

Clicking on one of the connections, shows the **License Monitoring Details** page, described above.

6 Troubleshooting

- [License Activation Issues](#)
- [Refreshing Licenses Page](#)
- [Changing WIBU CodeMeter Runtime](#)

6.1 License Activation Issues

In case the license activation fails due to a network outage, the portal displays a short error message during the activation. The portal then redirects itself to the Licenses Page where a new option is available, **Continue License Transfer**.

The screenshot shows the Vizrt Licenses Page interface. At the top, there are navigation tabs: Customers, Admin, Licenses (selected), Containers, and Free Licenses. Below the navigation, there is a search bar and a 'Show 10 entries' dropdown. The main content is a table with columns: Ticket, Name, Order ID, QTY, End Date, Activated On, Container, and Status. The table contains two groups of licenses, each with a group header (e.g., '4V63S-2M97F-8BAS2-U373C-LGQ6C (5)'). The 'Continue License Transfer' button is highlighted with a red box.

| Ticket | Name | Order ID | QTY | End Date | Activated On | Container | Status |
|-------------------------------------|---|----------|-----|------------|--------------|----------------|---------------|
| ^ 4V63S-2M97F-8BAS2-U373C-LGQ6C (5) | | | | | | | |
| 4V63S-2M97F-8BAS2-U373C-LGQ6C | V3 TriCaster Now - TriCaster Now Bridge - (Network) | | 4 | 2025-01-25 | - | | Available |
| 4V63S-2M97F-8BAS2-U373C-LGQ6C | V3 Viz Arena - Developer Features - (Network) | | 3 | 2090-12-31 | - | | Available |
| 4V63S-2M97F-8BAS2-U373C-LGQ6C | V3 Viz Engine - Artist Preview - (Network) | | 9 | 2025-01-30 | - | | Available |
| 4V63S-2M97F-8BAS2-U373C-LGQ6C | V3 TriCaster Now - TriCaster Now Bridge - (Network) | | 1 | 2025-01-25 | - | | Available |
| 4V63S-2M97F-8BAS2-U373C-LGQ6C | V3 Viz Arena - Developer Features - (Network) | | 2 | 2090-12-31 | 2024-03-05 | 130-2925769937 | Activated |
| ^ B4EW6-KH694-N279S-7RY33-U226H (5) | | | | | | | |
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - 4K Video Enablement - (Network) | | 1 | 2025-03-01 | - | | Available |
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - Artist - (Network) | | 1 | 2025-03-01 | 2024-03-21 | 130-1540195032 | Not completed |
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - Artist Preview - (Network) | | 1 | 2025-03-01 | - | | Available |
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - Bone&Skin Live Motion Capture - (Network) | | 1 | 2025-03-01 | - | | Available |
| B4EW6-KH694-N279S-7RY33-U226H | Viz Engine lmi1 - Chroma FX - (Network) | | 1 | 2025-03-01 | 2024-03-04 | 130-3874608740 | Activated |

Showing 1 to 10 of 151 entries (filtered from 163 total entries) Previous 1 2 3 4 5 ... 16 Next

Buttons: [Activate Licenses](#) [Re-Host Licenses](#) [Continue License Transfer](#)

With this option, the portal can pick up any open license activation and complete it.

6.2 Refreshing Licenses Page

There is a known behavior on the Licenses Page, that it automatically refreshes the browser window every few seconds. This happens when no CodeMeter Runtime software is installed on the computer the License Portal is opened.

To resolve this issue, either install the CodeMeter Runtime, that can be downloaded from the [Account](#) section, or switch to a different page in the portal and then go back to the Licenses Page.

6.3 Changing WIBU CodeMeter Runtime

When changing the CodeMeter Runtime version on a machine with a Software Container installed, the Software Container corrupts itself due to a security mechanism implemented. It is

recommended to re-host the licenses back to the portal before performing the upgrade and using a new Software Container once the update is done.

7 FAQ

This page contains answers to the following frequently asked questions:

- [Can Licenses be Updated during Operation?](#)
- [Local License on Virtual & Cloud Environments](#)
- [How to Handle a Corrupted WIBU Software Container?](#)
- [Upgrading Sentinel Licenses to WIBU Licenses](#)

7.1 Can Licenses Be Updated During Operation?

When the ticket activation process starts, any license verification calls of Vizrt software are temporarily blocked. This means that the current operation runs without interruption against the former license status until the ticket activation process is completed.

7.2 Local License On Virtual & Cloud Environments

When having a SW Container installed on the same machine as the Vizrt Software Products should run, the CodeMeter WebAdmin needs to be configured as [network server](#). The server in the [server search](#) list needs to be set to localhost or 127.0.0.1. The Vizrt software product needs to be configured to check for a license on the network as well.

7.3 How To Handle A Corrupted WIBU Software Container?

Changes in the hardware configuration of a computer (replacement of a motherboard, graphic card, CPU, ...) are the most common reasons for a corrupt software base license container. In this case, the license can no longer be used and the container must be deleted by Vizrt. You must then request a new license from your regional first-level support.

In order to receive a replacement license, please provide us the following documents:

- Official statement that describes the case (hardware is broken or stolen, ...).
- Photos of damaged hardware.
- In case of stolen parts, enclose the notice of loss.
- ID of the corrupt container or the computer name from which the container is located.

7.4 Upgrading Sentinel Licenses To WIBU Licenses

Customers are required to discuss license migration from Sentinel to WIBU with their manager or the CS team, who then reaches out with relevant information to the Licensing team. There is a set definition of how Sentinel Dongles are translated to WIBU License Tickets. There are no automated upgrades in the portable once WIBU 3.0 is launched.

7.4.1 Upgrade Process Steps:

1. Customer defines the Sentinel dongles to upgrade, and the current use case of the licenses.
2. Vizrt provides temporary WIBU tickets with replacement licenses.
3. Customer tests the WIBU licenses to confirm functionality of the systems with the new licenses.
4. Customer returns permanent Sentinel dongles to Vizrt, or requests temporary licenses for the old dongles and provides prove of application of the temporary licenses on the dongles.
5. Vizrt provides permanent extension of the WIBU license tickets.